



VisibleThread Readability On-Prem Deployment Overview

Version 2.4.5 July 2020

Copyright 2020 VisibleThread Limited. This document is the copyright of VisibleThread Limited and may not be reproduced in whole or in part without the consent of VisibleThread Limited. The document is not intended for production and is furnished "as is" without warranty of any kind. All warranties on this document are hereby disclaimed including the warranties of merchantability and fitness for a particular purpose.

Trademarks

© 2020 VisibleThread™ is a registered trademark of VisibleThread Limited. All rights reserved. All other trademarks are the property of their respective owners.

VisibleThread Deployment Overview

DEPLOYMENT OVERVIEW


A VisibleThread Readability deployment involves a single server:

- **VisibleThread Readability Server** hosts a web browser-based application.

The diagram below illustrates the server deployed on-prem (inside your organization) including user and system interactions.

VisibleThread Architecture for on-prem deployment

This diagram describes the VisibleThread Servers - **VT Readability(+Email Service)/Insights** and their interaction/usage by end-users and administrators.



We provide two ways to deploy VisibleThread software on-premise:

- A **Red Hat package** (a `visiblethread-xxx-.rpm` file) that you install into your Red Hat Operating System.
- A pre-packaged **Virtual Appliance** (a Virtual Machine (VM) / `.ova` file) that you import into your virtualisation infrastructure. The VM contains a pre-installed Ubuntu Operating System plus VisibleThread components.

An on-premise VisibleThread deployment has the following properties:

- Runs inside your organization's network/firewall & is fully under your control. No external access required.
- OS security/patching fully under your control.
- Initial install and application upgrades done by your IT team.
- Low IT management overhead – application upgrades are made available twice a year; your IT team can install the upgrades directly.

- Email/phone/screen-sharing support is available from VisibleThread staff.
- You can optionally setup a test/staging server to try out upgrades before rolling out to production.
- All end-user access is secured over https using a web browser.
- There is an option to encrypt data at rest.
- With a Virtual Appliance deployment, you can use virtualisation backup/restore.

MINIMUM REQUIREMENTS

Below are the minimum requirements for the server:

VisibleThread Readability	
12GB RAM	
2 CPU Cores	
220GB disk	
Install type	
Red Hat package install	Virtual Appliance install
Red Hat Enterprise Linux RHEL 7.2 - 7.6	VMware vSphere

VT Readability Email Server- Requirements

1. An IMAP or POP3 mailbox to receive documents for analysis. Users email documents to this mail box. The Readability application will require the credentials to read messages from this mailbox
2. An SMTP email account that the Readability server can use to send out email replies.

INSTALLED COMPONENTS

The following table lists the components/dependencies installed with the application:

VisibleThread Readability
PostgreSQL 10
Apache web server 2.4
Apache Tomcat 8.5

NETWORKING

VisibleThread Readability is a web application. End-users and system admins access the application via their web browser over https.

All end-user communication with the application is via port 443 (https)

If using the Virtual Appliance deployment model, IT administrators access the VisibleThread server console via ssh on port 22.

All communication with VisibleThread Virtual Appliance uses these ports:

- Port 443 is used for https communication via the web browser.
- Port 22 is used for ssh and secure ftp access.
-

VisibleThread Readability does not require access to any external location.

With a Virtual Appliance deployment, the VisibleThread Server is configured to use DHCP to pick up an IP address automatically on startup. It is recommended you allocate a designated static IP address to the server on initial deployment.

SSL Termination

The VisibleThread Readability installation includes installation of an Apache web server with a self-signed certificate. This allows the application to run “out of the box”. You can install your own SSL certificate on the box should you choose.

Alternatively, you can choose to front the Readability web application with your own existing Web Server or Load Balancer (e.g. Microsoft IIS, F5) and have the SSL configuration handled by your existing service. Please contact support@visiblethread.com for more details.

ENCRYPTION AT REST

VisibleThread Readability supports the encryption of the data volume using AES. Contact our support team at support@visiblethread.com for more details.

USER MANAGEMENT

VisibleThread provides a web application to manage users and application licenses. User accounts are created and managed locally on your VisibleThread installation using the web browser-based application.

Each user must be created with a username (email address) and a password. Passwords are salted, securely hashed and stored locally in the VisibleThread database.

Users can be given ‘Admin’ privileges which allows them add/remove users from the system and configure common user settings. A ‘System Admin’ role also exists to allow system configuration such as data retention policies, email integration etc.

Single Sign-On (SSO) with SAML 2.0 is now available with VisibleThread Readability version 2.4.4 and above. See our configuration help guide for more details.

AUDITING

We support review & audit of user activity including user login, add/remove documents, generate reports. All user activity is tracked in our application database and is available for review.